

Supervisord

```
apt-get install supervisor
systemctl enable supervisor
service supervisor restart
service supervisor status
```

```
nano /etc/supervisor/conf.d/np_natlog.conf
```

```
[program:np_natlog]
environment=PATH="/usr/bin"
directory=/usr/local/nodeny/
command=perl nokernel.pl -m=natlog -d &
autostart=true
autorestart=true
stderr_logfile=/var/log/nodeny/np_natlog.err.log
stdout_logfile=/var/log/nodeny/np_natlog.out.log
```

```
mkdir -p /var/log/nodeny
supervisorctl reread
supervisorctl update
```

```
nano /etc/supervisor/conf.d/np_natlogsort.conf
```

```
[program:np_natlogsort]
environment=PATH="/usr/bin"
directory=/usr/local/nodeny/
command=perl nokernel.pl -m=natlogsort -d &
autostart=true
autorestart=true
stderr_logfile=/var/log/nodeny/np_natlogsort.err.log
```

```
stdout_logfile=/var/log/nodeny/np_natlogsort.out.log
```

```
supervisorctl reread  
supervisorctl update
```

синтаксис перезапуску програм

```
supervisorctl restart <name1> [ <name1> ... <nameN>]
```

перезапуск програм

```
supervisorctl restart np_natlog np_natlogsort
```

вiд команди

```
np_natlog          RUNNING    pid 7558, uptime 0:03:16  
np_natlogsort      RUNNING    pid 7561, uptime 0:03:15
```

перевірити статус

```
supervisorctl status np_natlog np_natlogsort
```

вiд команди

```
np_natlog: stopped  
np_natlogsort: stopped  
np_natlog: started  
np_natlogsort: started
```

URLS

<https://adw0rd.com/2012/11/02/python-supervisor/>

<http://www.supervisord.org/>

CeSi - Centralized Supervisor Interface

From:

<https://ndp.pp.ua/> - **my NoDeny Wiki**

Permanent link:

<https://ndp.pp.ua/doku.php/debian/supervisord>

Last update: **04/12/2024 20:52**

